



Using Multiple Mobis in a Classroom

Workspace v. 8.90

The Multi User  feature allows for two or more people to interact with the Interwrite Workspace Software. You can set up multiple Interwrite Mobis to display on the board at the same time.

Setting Up Multi User Functionality in Workspace

1. With Workspace open, click the Multi User icon in the bottom right corner .

The Multi User Page Setup window opens.

2. If you have not already done so, connect the devices you need to use in Workspace. You can add up to 9 devices. The connected devices display in the Available Devices Area.

3. Select the Multi User **Page Setup** you want to use.


Determine if you want to use **Collaborative** or **Defined** areas. The selected grid displays in the Multi User Area.

4. Select the device and drag it to the area needed.

The Device will be able to be viewed within the area displayed within the Multi User Page Setup window.


TIPS for Classroom Management


A collaborative classroom environment leaves a lot of room



for students to explore and can lead to distracting behaviour. To help you control this, here are some helpful features:

1) Naming your Mobis – It is possible to change the name of the Mobis to more easily identify


which one is writing on the screen. To set this, click on the eInstruction icon  in the System Tray (bottom right corner of the screen for Windows, top right for Mac) and click **eInstruction Device Manager**. You should see all the Mobis that you have connected. Double-click on a Mobi. The Properties window will appear. Enter the name of your choice into the field at the top.





Showing/Hiding the Mobi names on cursor – This is done in the **Workspace Preferences** (Workspace Menu > Preferences >

Options Tab). Check or uncheck the box beside “Show Tablet ID on cursor.”

2) Presenter Mode – When multiple Mobis are connected, you can make one of them the “Presenter.” The Mobi that is marked as the presenter overrides all other Mobis when not in Multi-User mode so that multiple pads aren’t fighting for control of the computer mouse. One of them may already be the Presenter, and will be marked with a figure in a suit. In the example to the right, the Mobi “Matt” is the Presenter. To assign a new presenter, select another Mobi and then click the Presenter button beside the Lock button.

3) The Lock Button -  This button can be added to your Workspace Toolbar, and locks out all Mobis that are not the Presenter. To unlock specific Mobis, open the **Device Manager** (as

above), select a Mobi and click on the unlock button.  You can also find the Device Manager while a Multi-User page is open by clicking the Multi-User icon and clicking **Edit**

Devices, then clicking the Device Manager icon.  This button can also be added to your Workspace toolbar.